



Tampere (Finland) / Offenburg (Germany), 6 March 2017

Please be informed that **Testwell CMT++ version 6.0.1** has been released.

This is a small maintenance version having a couple bug fixes and enhancements. See the VERSION.TXT excerpt below for details.

Support customers can download the new version from Testwell Customer Pages in the normal manner.

Olavi Poutanen
Testwell

-----Excerpt of VERSION.TXT:

```
Testwell Oy                                CMT++ System Version 6.0.1
Verifysoft Technology GmbH
28 February 2017
```

This file describes the changes in successive versions of Testwell CMT++, Complexity Measurement Tool for C/C++/C#. The latest version is described first.

CMT++ v6.0.1 (28 February 2017):
=====

This revision 6.0.1 of CMT++ has the following version numbers in its components:

basic CMT++ tool	6.0.1	(was 6.0, seen on the screen/reports)
cmt2html	2.4	(unchanged, seen by invoking the cmt2html with -h option and in HTML report header)
CMT++ GUI	2.11	(unchanged, seen on "About" pane, available on Windows only)

The enhancements and bug fixes in this CMT++ revision are:

- [cmt] Bug fix: In 'namespace NS {functions}' the functions remained unmeasured in some situations, if the construct was preceded by '#include MACRONAME' line.
- [cmt] Bug fix: When function return type was a struct or a class and function parameters were on next line, for example:
'struct SS foo \n (parameterlist) {body}'
the function name 'foo' was lost in the report (got replaced by '\n').

- [cmt] Change: The license check-out retrial count (used for some reasons before) is lowered from 3 to 1.
- [cmt] Change: At Windows, when license check-out fails, the Flexlm License Finder popup is no more started, regardless if environment variable FLEXLM_BATCH is set or not. Instead the cmt-machinery error message is written straight away.
- [general] As the CMT++ behavior has not essentially changed the CMT++ User's Guide is still at v6.0 level.

CMT++ v6.0 (25 August 2015):

=====

For this version, please have a look to

<http://www.verifysoft.com/cmtpp60.pdf>

For further questions, please call +49 781 127 8118-0